

This page has been deprecated in favor of  
Ubuntu 16.04 (xenial) LTS and ROS Kinetic

## Indigo Prerequisite Software Setup

The following instructions should be used if you are running a Ubuntu 14.04 (trusty) derivative, including Linux Mint 17.x

```
sudo sh -c 'echo "deb http://robosub.eecs.wsu.edu/repo/ /" >
/etc/apt/sources.list.d/robosub.list'
wget http://robosub.eecs.wsu.edu/repo/repository_key -O - | sudo apt-key add -
sudo sh -c 'echo "deb http://packages.ros.org/ros/ubuntu trusty main" >
/etc/apt/sources.list.d/ros-latest.list'
wget https://raw.githubusercontent.com/ros/rosdistro/master/ros.key -O - |
sudo apt-key add -
sudo sh -c 'echo "deb http://packages.osrfoundation.org/gazebo/ubuntu trusty
main" > /etc/apt/sources.list.d/gazebo-latest.list'
wget http://packages.osrfoundation.org/gazebo.key -O - | sudo apt-key add -
sudo sh -c 'echo "deb https://packagecloud.io/github/git-lfs/ubuntu/ trusty
main" > /etc/apt/sources.list.d/github_git-lfs.list'
wget https://packagecloud.io/github/git-lfs/gpgkey -O - | sudo apt-key add -
sudo aptitude update
sudo aptitude install robosub robosub-simulator git-lfs
git lfs install
```

To configure your path to know about ROS software, run

```
echo "source /opt/ros/indigo/setup.bash" >> ~/.bashrc
```

Next, continue with the instructions on the [getting start page](#).

From:

<http://robosub-vm.eecs.wsu.edu/wiki/> - **Palouse RoboSub Technical Documentation**

Permanent link:

[http://robosub-vm.eecs.wsu.edu/wiki/cs/getting\\_started/indigo/start?rev=1534228760](http://robosub-vm.eecs.wsu.edu/wiki/cs/getting_started/indigo/start?rev=1534228760)



Last update: **2018/08/13 23:39**